



# HOW TO CONNECT TO THE AA WIRELESS NETWORK (AA-WLAN)


## Windows Vista (SP1 or later)

Click Start, type “Network” in the search field and select **Network and Sharing Centre**. Click on **Set up a new connection or network** (in the left hand column).



In the **Set Up a Connection or Network** window, choose **Manually connect to a wireless network**, and click **Next**.



In the **Network Name** field, type in **AA-WLAN** (in capital letters). Change the **Security type** to **WPA2-Enterprise**. The **Encryption Type** should already be set to **AES**. Tick the **Connect Even If the Network Is Not Broadcasting** checkbox. The **Start this connection automatically** should already be ticked. Click **Next**, and in the **Successfully added AA-WLAN** window, click on the **Change connection settings** option.




In the **Connection** tab of the AA-WLAN Wireless Network properties window, uncheck the **Connect to a more preferred network if available** checkbox. Click the **Security** tab and select **Settings**.



# HOW TO CONNECT TO THE AA WIRELESS NETWORK (AA-WLAN)

In the **Protected EAP Properties** window, clear the **Validate server certificate** checkbox . The **Enable Fast Reconnect** checkbox should already be ticked, and the **Authentication Method** should be **Secured Password (EAP-MSCHAP v2)**.



Click **Configure**, and a smaller window should appear, titled **EAP MSCHAPv2 Properties**. Clear the **Automatically Use My Windows**

**Logon Name and Password (And Domain If Any)** checkbox, and click **OK**.

Click **OK** in the **Protected EAP Properties** window, click **OK** in the **AA-WLAN Wireless Network Properties** window, click **Close** in the **Wireless Network Connection Properties** window and close the **Manage Wireless Networks** window. In a few moments, a speech bubble (**Additional information is required to connect to AA-WLAN...**) should appear in the bottom right corner of your screen. Click on it, and you will be presented with a window asking you for your user credentials.

Type in your username, adding **@aaschool.ac.uk** at the end (for example, **sam.smith@aaschool.ac.uk**), and password in the fields provided. Clicking **OK** will connect you to **AA-WLAN**. Finally, click **Work network** in the Set Network Location window appears.

